


SyriusApplet架构实现

架构不变式：

```
view = Observe(action)
```

单向数据示意图：



变化侦测篇：

```

function observe(state, $setCurrentActionInfo,$getLastActionInfo) {
  let $_NEW_CURRENT_ACTION_INFO = {};
  // Listen to GODIVA events
  window.actionRequestCallback = (actionRequestJson) => {
    // Read the last action info
    let $_LAST_ACTION_INFO = $getLastActionInfo();
    // Save the new action info of GODIVA
    $_NEW_CURRENT_ACTION_INFO = $setCurrentActionInfo(evalActionReqToObj(actionRequestJson));

    // OBSERVE CHAIN
    let chain = moveToPackBindRegion
      .after(bindPack)
      .after(moveToPickingProduct)
      .after(pickingProduct)
      .after(packageRegion)
      .after(moveToHoldRegion)
      .after(moveToPackageRegion)
      .after(moveToException)
      .after(moveToBindCarrier)
      .after(bindNewCarrier)
      .after(waitNewTask)
      .after(exceptionRegion)
      .after(moveToShelfStorageRegion)
      .after(onShelf)
      .after(onShelfOver)
      .after(moveToWormholeRegion)
      .after(waitingForWormhole);

    try {
      let nextActionInfo = window.GodivaJsInterface.getNextAction();
      let actionReq = JSON.parse(nextActionInfo);
      let nextAction = evalActionReqToObj(actionReq);
      console.log(" nextAction", nextAction);
      chain(evalActionReqToObj(actionRequestJson), state, nextAction, $_LAST_ACTION_INFO);
    } catch (error) {
      chain(evalActionReqToObj(actionRequestJson), state, {}, $_LAST_ACTION_INFO);
    }
  }
}

```

模板编译篇：

```

let syriusApplet = new SyriusApplet({
  applet: <YOUR_APP>,
  state: {
    MOVE_TO_PACK_BIND_REGION: function () {

    },
    WAIT_NEW_TASK: function () {

    },
    MOVE_TO_BIND_CARRIER_REGION: function () {

    },
    MOVE_TO_SHELF_BIND_REGION: function () {

    },
    MOVE_TO_HOLD_REGION: function () {

    },
    MOVE_TO_EXCEPTION_REGION: function () {

    },
    DEAL_EXCEPTION: function () {

    },
    BIND_PAYLOAD: function () {

    },
    BIND_SHELF_PAYLOAD: function () {

    },
    TEAR_DOWN_OLD_PAYLOAD: function () {

    },
    BIND_NEW_CARRIER: function () {

    },
    MOVE_TO_PICK_PRODUCT: function (nextAction) {

    },
    PICKING_PRODUCT: function () {

    },
    EMERGENCY_STOP: function () {

    },
    MOVE_TO_SHELF_STORAGE_REGION: function (nextAction) {

    },
    ON_SHELF: function () {

    },
    ON_SHELF_OVER: function () {

    },
    MOVE_TO_WORMHOLE_REGION: function () {


    },
    WAITING_FOR_WORMHOLE: function () {

    }
  },
  work: function (observe) {
    return observe(this.$state, this.$setCurrentActionInfo, this.$getLastActionInfo);
  },
});

```

生命周期篇：

综述：



```
function SyriusApplet(options) {
    this._init(options);
}
```

```
initMixin(SyriusApplet);
```

初始化阶段 (initMixin)

```
function initMixin(SyriusApplet) {
    SyriusApplet.prototype._init = function (options) {
        const vm = this;
        vm.$options = options;
        vm._self = vm;
        this.$applet = vm.$options.applet;
        this.$state = vm.$options.state;
        this.$work = vm.$options.work || {};
        this.$setCurrentActionInfo = (actionJson) => {
            vm.$currentActionInfo = actionJson;
            return vm.$currentActionInfo;
        }
        this.$getLastActionInfo = () => {
            return vm.$currentActionInfo
        }
        /**
         * Function
         * init function.prototype
         */
        init();
        /**
         *
         * init event
         */
        initEvent(vm);
        /**
         *
         * init state(observe)
         */
        if (this.$applet && typeof this.$work === "function") {
            this.$work(observe);
        }
    }
}
```

初始化阶段 (init)

```
function init(){
    Function.prototype.after = function(fn) {
        let self = this;
        return async function() {
            let ret = await self.apply(this, arguments);
            if (ret === "nextSuccessor") {
                return fn.apply(this, arguments);
            }
            return ret;
        }
    };
}
```

初始化阶段 (initEvent)

```
let eventListenersInterface = window.EventListenersInterface;

initGodivaEvent(vm);
initVoiceLightEvent(vm, eventListenersInterface);
initScannerEvent(vm, eventListenersInterface);
initMoveManager(vm, eventListenersInterface);
initPoseEvent(vm, eventListenersInterface);
initEquipmentStatusEvent(vm, eventListenersInterface);
initKnowledgeBaseEvent(vm);
initCommonEvent(vm);
initLaunchEvent(vm);
initBaroEvent(vm, eventListenersInterface);
```

实例方法篇：

数据相关

```
vm.$options :options
vm.$applet  :$appletvuesyriusApplet
```

```
vm.$currentActionInfo :actionDetailInfo<Object>
```

指令篇：

通用事件 (initCommonEvent)

设备状态事件 (initEquipmentStatusEvent)

```
function initEquipmentStatusEvent(vm, eventListenersInterface){
  let equipmentStatus = new EquipmentStatus(eventListenersInterface);
  vm.onceCheckCameraStatus = async function(){
    let status = await equipmentStatus.onceCheckCameraStatus();
    console.log(status);
    return status
  }
}
```

godiva消息事件 (initGodivaEvent)

```
function initGodivaEvent(vm) {
  let godivaReportEvent = new GodivaReportEvent();
  let godivaTeleportEvent = new GodivaTeleportEvent();
  let godivaTaskEvent = new GodivaTaskEvent();
  let godivaInitEvent = new GodivaInitEvent()

  /**
   * godiva
   * report data to godiva
   * @param currentAction
   */
  vm.reportEvent = function(currentAction){
    godivaReportEvent.reportEvent(currentAction);
  }
  vm.onNotifyListen = function(resCallbackObj){
    godivaReportEvent.onNotifyListen(resCallbackObj);
  }

  /**
   * godiva calculate witch floor can arrive result
   * godiva
   * @param startNode
   * @returns {*}
   */
  vm.getOutGoingNodesForTeleport = function(startNode){
    return godivaTeleportEvent.getOutGoingNodesForTeleport(startNode);
  };
  vm.onCancelTask = function(){
    return godivaTaskEvent.onCancelTask();
  };
  vm.onPauseTask = function(){
    console.log("pauseTask");
    return godivaTaskEvent.onPauseTask();
  };
  vm.onResumeTask = function(){
    return godivaTaskEvent.onResumeTask();
  };
  vm.onGetAllTask = function(){
    return godivaTaskEvent.onGetAllTask();
  }
  vm.onGetAllTaskInPool = function(){
    return godivaTaskEvent.onGetAllTaskInPool();
  }
  vm.godivaConfig = function(){
    return godivaInitEvent.godivaConfig();
  }
}
```

知识库事件 (initKnowledgeBaseEvent)

启动事件 (initLaunchEvent)

移动事件 (initMoveManager)

```

function initMoveManager(vm, eventListenersInterface) {

    let move = new Move(eventListenersInterface);
    vm.safeInitNavigation = function (callback) {
        return move.safeInitNavigation(callback);
    }
    vm.safePauseMove = function (callback) {
        return move.safePauseMove(callback);
    }
    vm.safeResumeMove = function (callback) {
        return move.safeResumeMove(callback);
    }
    vm.isPauseMove = async function(){
        return await move.isPauseMove();
    }
    vm.getLastMoveStatus = function(){
        return move.lastMoveStatus;
    }
}

```

位姿事件 (initPoseEvent)

对外暴露的API部分

```

function initPoseEvent(vm, eventListenersInterface) {
    let pose = new Pose(eventListenersInterface);
    vm.safeSwitchMapByChangeLayer = function(mapLayerName, loadingCallback){
        return pose.safeSwitchMapByChangeLayer(mapLayerName, loadingCallback);
    };
    vm.listenRobotPose = function(callback){
        pose.listenRobotPose(callback);
    }
    vm.unbindListenRobotPose = function(){
        pose.unbindListenRobotPose();
    };
    vm.listenLayerPose = function(callback){
        pose.listenLayerPose(callback);
    };
    vm.unbindListenLayerPose = function(){
        pose.unbindListenLayerPose();
    };
    vm.safeManualPose = function(wormhole, loadingCallback){
        return pose.safeManualPose(wormhole, loadingCallback);
    };
}

```

扫码枪事件 (initScannerEvent)

对外暴露的API部分

```

function initScannerEvent(vm, eventListenersInterface) {
    let scanner = new Scanner(eventListenersInterface);

    vm.unbindScan = function () {
        scanner.unbindScan();
    }
    vm.scanCode = function (resCallbackObj = {
        success: function () {
        }, fail: function () {
        }
    }) {
        scanner.onScan(resCallbackObj);
    }
}
initVoiceLightEvent
safeRetry

```

全局API篇：

init.js

```
function init(){
  Function.prototype.after = function(fn) {
    let self = this;
    return async function() {
      let ret = await self.apply(this, arguments);
      if (ret === "nextSuccessor") {
        return fn.apply(this,arguments);
      }
      return ret;
    }
  };
}
```